Click to verify

If you want to access your old laptop but youve forgotten its password, the ideal method is to factory reset it. Basically, this erases all your data, including the sign-in option, and restores the operating system to default. Generally, logging in to your laptop should be easy if you have set up a Microsoft Account. This is because you could easily reset your password even if forgotten. But you can possibly not do it if you got it from your friend or bought a pre-owned laptop. In such a case, the only option left is to restore it to factory settings. So, if youre also stuck on the sign-in screen and want to access the laptop, youre at the right place. Here, we have explained what a factory reset does and some easy techniques to do without a password. Factory reset is an option within Windows OS that sends the PC to its default system state. Usually, we perform the factory reset on Windows to solve any hard drive and OS-related issues. Since this option deletes every software thats creating issues on your system, we recommend factory resetting your laptop if youre trying to sell it or you recently bought a used one. This way, even the lagging issues get resolved, and you can use the old laptop as if its brand new. Factory resetting can be easily done within the Settings when youre already logged in to your laptop. Well, youll just need to go to System > Recovery > Reset This PC. Then, move ahead with the necessary steps. However, you need to use alternative methods if you do not remember your laptops password. In this section, we have explained the proven ways to factory reset your Windows 11 laptop. To enter the Windows Recovery Mode, we recommend checking the user manual as every manufacturer has different dedicated keys to open it. Generally, most PCs can navigate you to the recovery screen by pressing the F11 key when Windows is booting. Moreover, you can use bootable media and select Repair your computer to open the Windows Recovery Mode. Also, you can directly navigate to this screen from the login screen, and here are the involved steps you need to follow: Once youre on the log-in screen, press the power icon in the windows bottom-right corner.Now, while holding the Shift key, press the Restart option.Then, you may need to choose the Restart Now button if any other apps are running.Wait for several seconds until your system takes you to the Windows Recovery Mode.Once the Choose an option window loads, select Troubleshoot.Next, click on Reset this PC.Then, youll be shown two options Keep my files and Remove everything. If you want to keep your personal files, choose the first option. But if you want your laptop to restore everything to its default settings, select the latter.If you selected Remove everything, youd likely get two more options Cloud Download and Local Reinstall. Choose one as per your requirement.Again, youll need to select either Just remove my files or Fully clean the drive. Well, we suggest selecting the second option if you wish your entire system to be restored.Now, click on the Reset button to start the reset process. This may take more than an hour.Once the factory reset is complete, the setup window pops up. Now, you can move ahead and complete the system setup.Youll be asked to create a Microsoft account when this is completed. If you already have one, log in using your credentials. Otherwise, create an account and ensure you keep a password you remember. Interestingly, every manufacturer offers a recovery partition that can be accessed using a dedicated function key. Once you enter the recovery screen, youll be able to perform the following operations:Factory reset your laptopPerform backup and restore managementBack up user dataCreate a factory state diskCreate a disk copy In this section, we have included the steps for some of the most popular laptops. If we have missed out on yours, the process is quite similar to any of them. So, all you have to do is read the user manual or refer to the internet to check the dedicated key for your laptop. Samsung doesnt just manufacture mobile phones but is also equally popular for producing laptops. For demonstration purposes, we have used Samsung Notebook here. Nonetheless, the steps should be similar for every other Samsung laptop too: Power on your device and wait until the Samsung logo pops up.Now, long hold the F4 key, and youll notice a Please Wait signal on the screen.After several seconds, your laptop initiates Samsung Recovery.Wait until the Terms of Use page loads. Scroll down and click on the Agree button.Next, in the Samsung Recovery window, choose Computer factory reset.Then, check the Verify backup data option so that all your files and data will be backed up.Now, choose the Start factory reset option and wait until the reset is complete.Once the reset is complete, your PC restarts, where you can log in to your Microsoft account and set the desired password. Lenovo has adopted OneKey Recovery to factory reset your laptop without needing a password. However, this option is available only on the Ideapad series. For demonstration purposes, weve used the Lenovo G40 model. Nonetheless, the steps should be similar to other models as well: Find and press the Novo button thats generally located on the left side of your laptop. You may need a pointed object to press the button.Once the Novo Button Menu pops up, choose System Recovery. In some models, you can press the F10, F8, or F12 keys to navigate here.Wait for several seconds until the OneKey Recovery window opens up.Now, choose either Restore from initial backup or Restore from users backup and hit the Next button.Then, click the Start button to start a factory reset on your Lenovo laptop.Once the recovery is complete, set up Windows as per the screen instructions. Dell users can factory reset their laptops using the SupportAssist OS Recovery feature. However, this option is only available on some models. Go through the below guide to restore your settings to default on a Dell laptop: Power on your PC and hit the F12 key multiple times to enter BIOS mode. In some models, you might need to use other keys. So, we suggest looking up the internet to check the key that works for you.Under Other Options, choose SupportAssist OS Recovery.Then, wait for about a minute until the feature loads and select Restore System.Next, click on the Restore Now button.Continue hitting Next until the Do you want to backup your file message appears. Choose Backup if you want to; else, you can choose Skip.Now, select a reason why youre performing the reset. Then, click on Next.Wait for the factory reset to complete and tap on the Finish button.Once the reset is complete, you can proceed with the instruction and install Windows. Generally, both resetting and reinstalling Windows are applicable if youre trying to delete everything from your PC. So, if you have an original disk or its feasible to create a bootable drive, you can easily reinstall your OS. To reinstall Windows using an installation media, youll need another Windows PC and an 8 GB or higher storage USB drive to make it bootable. Also, download Rufus from their official site as the below steps involve using this open-source application: Firstly, visit Microsofts official website on your other PC and download the Windows 11 ISO file.Now, launch Rufus and under Device, choose your flash drive.Next, under Boot selection, select the downloaded ISO file.Then, click on the START button to make your drive bootable.Once a warning message pops up, choose Ok.Unplug the USB cable and insert it into your laptop.Power on your laptop and wait until the Windows Setup window pops up.Next, choose the language, time, and keyboard. Then, select Next to continue.Now, click on the Install button.If you have the activation key, enter it. Else, you can choose I dont have a product key from the bottom of the dialogue box.Then, select the OS and proceed by clicking on Next.Check the Microsoft Software License Terms and again click on Next.Now, youll get two options Upgrade: Install Windows and keep files, settings, and applications and Custom: Install Windows only.If the supported version is already running, we recommend choosing the first option as this will reinstall Windows without losing data. Nonetheless, you can choose the latter one if you want the system to start from default.Then, choose a drive to create a partition. While doing so, ensure you delete all the other drives.Finally, wait for Windows to get installed. Once done, youll be navigated to a new window where you can set up a Microsoft account and start using the OS from scratch. Dell laptop is a foremost choice for most laptop users because of its convenience and some of the best features. However, sometimes you want to delete the whole record from your laptop like if you want to sell the laptop to someone and want to factory reset it. It becomes difficult for some people to factory reset Dell Inspiron without password. You can easily learn methods on how to factory reset Dell laptop without password. Some of these methods are given below and they are all can be used to Dell latitude 5420Dell inspiron 15, XPS, Chromebooks and more. If you are a Windows 8 or 10 user and you have forgotten your Dell laptop's password, you don't have to worry about it because you can factory reset Dell Inspiron 1525 without password. You just have to follow these steps. Step 1. First of all, click the start button. Step 2. Go to settings and select "update & security" and reset this PC. Step 3. Then you will have an option to remove everything and reinstall Windows. Windows Vista and 7 asks you to enter password while restoring factory settings. If you have forgotten your password then you should remove it by making a CD from another computer you have access to. Get done with password recovery and then you can proceed further towards restoring factory settings. Follow these steps to restore factory settings. Step 1. Turn the laptop on and press "F8" as soon as you see Dell logo on the screen and then you will see "advanced boot options'. Step 2. You need to select "repair your computer" and then press enter and you will see "system recovery options" screen. Step 3. Find the keyboard layout of yours and click next. Step 4. You will need to give user name and password but if you have removed it then you can leave the field blank. Step 5. Choose "Dell datasafe restore and emergency backup" or "Dell factory image restore" and "Dell backup and recovery managers" from system recovery options. Step 6. Then you need to follow the instructions given to you in order to restore factory settings of your Dell laptop. Step 7. These instructions will ask you to go "next". Step 8. Then check the box which says "yes, format hard drive and restore system software to factory condition" and then click "next". Step 9. The resetting process starts. It might take a few minutes, wait till it is finished and then click on finish. Follow these steps to restore factory setting on Windows XP of your Dell laptop. Step 1. Restart your Dell computer and then keep pressing "ctrl + F11" till you see Dell logo appearing and disappearing.Step 2. Click on "restore and then "confirm".Step 3. Resetting process will begin.Step 4. Once the process is completed, click "finish". If you are locked out and can't remember your password on Windows 10, you can simply click the power button and then click Restart, then press shift key. You will see a blue screen, choose "Troubleshoot" and then "Reset this PC". If you can't see the Troubleshoot screen, you can remove the password using PassFab 4WinKey and then get access to the PC to factory reset it without password. This software can easily reset Windows login password on your Dell computer within a few minutes, especially for those users who used Administrator as login password. Here is the video tutorial about the steps. Step 1. Download and launch the tool from official websiteand select click "start password reset to start". Step 2. Format your USB by clicking "Start burning". Then click "Nexy" to burn the tool on your USB. It will take a few minutes. Step 3. Now you can use the device to recover Windows password which was used for computer login. Attach this device to your laptop and restart your laptop and press "F12" or "ESC" and it will enter you in an interface called "boot menu interface". Step 4. Select the operating system you are using on your Windows and click "Next" button. Step 5. Select the locked account from different accounts including guest, admin or Microsoft account and choose "Remove Account Password" to unlock computer without password. Step 6. Your login password will be removed soon. Now restart your computer to end the process and you are going to sign in Dell laptop without any password. After removing the login password and get access to your Dell laptop, you can factory reset it in the computer settings, do that as the previous parts show. If you forget your administar password and cannot log in to your Dell, you can try the following: Step 1. On the login screen, click on the power icon located in the bottom right corner of the screen. While holding down the Shift key, click on "Restart."Step 2. Your computer will initiate a reboot and take you to the troubleshooting options screen. Click on "Troubleshoot." Step 3. Next, you will be presented with options to reset or refresh your computer. Click on "Reset your PC." Step 4. Click on "Next." The system will restart and begin preparing to reset the computer.Step 5. On the "Reset your PC" screen, click on "Remove my files only," and then click "Reset." 1. Restart your system.2. Press "F12" when the system restarts.3. Make sure the USB is plugged into the system.4. You will enter the Boot menu.5. Chose recovery from the USB section from the previous part. Q2. Can I factory reset the system from BIOS? Yes, you can factory reset the system from BIOS. However, it is important to note that resetting the BIOS will not erase your data. It will only reset the BIOS settings to their default values. Q3. How do I wipe my Dell computer clean and start over? You can try reset this pc option.1. Click on the Start button and type "reset".2. Select Reset this PC (System Settings).3. Under Reset this PC, select Get Started.4. Select the option to Remove everything. If you want to restore factory setting of your Dell laptop, then above mentioned methods are best for you and you can easily restore factory setting and format your laptop. Now you have much better understanding of restoring factory settings of Dell laptop without password. Remove or reset Administrator password instantly Reset Microsoft account password in minutes Delete or create Windows account if you want One click to create a Windows password reset disk (USB/CD/DVD) Support all computer brands like Dell, HP, Lenovo, Toshiba, etc. Compatible with Windows 11/10/8.1/8/7/Vista/XP and Server 2019 Free Download Free Download Share copy and redistribute the material in any medium or format for any purpose, even commercially. Adapt remix, transform, and build upon the material for any purpose, even commercially. The licensor cannot revoke these freedoms as long as you follow the license terms. Attribution You must give appropriate credit , provide a link to the license, and indicate if changes were made . You may do so in any reasonable manner, but not in any way that suggests the licensor endorses you or your use. ShareAlike If you remix, transform, or build upon the material, you must distribute your contributions under the same license as the original. No additional restrictions You may not apply legal terms or technological measures that legally restrict others from doing anything the license permits. You do not have to comply with the license for elements of the material in the public domain or where your use is permitted by an applicable exception or limitation . No warranties are given. The license may not give you all of the permissions necessary for your intended use. For example, other rights such as publicity, privacy, or moral rights may limit how you use the material. Have you ever found yourself locked out of your Windows 10 computer because you forgot the admin password? Dont worry; there is a way to reset your PC without it. This process can help you regain access to your computer without needing to input any passwords. Before we get into the nitty-gritty, its crucial to understand what these steps will do. Essentially, well be using Windows 10s built-in reset feature to restore your computer to its factory settings. This will remove all personal files, apps, and settings, so make sure to back up anything important before proceeding. To start, youll need to get to the Advanced Startup Options menu. This can often be done by restarting your computer and pressing the F11 key as it boots up. If youve followed the step correctly, your computer should boot into the Advanced Startup Options menu. This is where you can troubleshoot and recover your PC without needing to log in. Once youre in the Advanced Startup Options menu, use your arrow keys to navigate to Troubleshoot and press Enter. By selecting Troubleshoot, youre telling your computer that you want to access the options that can help fix problems with your PC. Under the Troubleshoot menu, youll see an option to Reset this PC. Select this option to begin the reset process. When you choose to reset your PC, Windows 10 will offer you two options: Keep my files and Remove everything. Given that you dont have the admin password, youll need to select Remove everything. The system will guide you through a series of prompts. Follow these carefully to complete the reset process. The on-screen instructions are straightforward. They will ask you to confirm that you want to reset your PC and may offer additional settings to choose from, such as whether to clean the drives as well. After completing these steps, your Windows 10 computer will reset to its default settings, and youll be able to set up a new admin password. Remember that all your data will be erased, so ensure that youve backed up everything you need. Always back up your data before performing a reset to avoid losing important files. Make sure your computer is plugged into a power source during the reset process to prevent interruption. If you cant access the Advanced Startup Options menu with the F11 key, you can also try using a Windows 10 installation disc or USB to boot and access the menu. Consider creating a password reset disk for future use to avoid this issue. After the reset, take the time to set up a new admin password that youll remember, or write it down and keep it in a safe place. If the F11 key does not work, you might have to use a Windows 10 installation disc or USB drive to boot your computer and access the Advanced Startup Options menu. If you have the admin password, you can choose the Keep my files option during the reset process. However, without the admin password, you must select Remove everything. The reset process can take anywhere from a few minutes to a few hours, depending on your computers speed and the amount of data being erased. Resetting Windows 10 will remove most viruses, but its not guaranteed to remove all malware. Its always a good idea to install a reputable antivirus program after resetting. Once the reset process has begun, its not recommended to cancel it as this can lead to issues with your operating system. Its best to allow the process to complete. Access the Advanced Startup Options menu by pressing F11 during boot. Navigate to and select Troubleshoot. Choose Reset this PC and then Remove everything. Follow the on-screen instructions to complete the reset. Resetting Windows 10 without an admin password may seem daunting, but its a straightforward process that can be a lifesaver when youre locked out of your computer. Just remember, this process will remove all your personal data, so its essential to back up everything beforehand. After completing the reset, youll have a fresh start with Windows 10, and you can set a new admin password to prevent future lockouts. Its also wise to create a password recovery disk or use a password manager to keep track of your credentials. With these tools and knowledge, youll never have to worry about being locked out of your Windows 10 computer again.Matt Jacobs has been working as an IT consultant for small businesses since receiving his Masters degree in 2003. While he still does some consulting work, his primary focus now is on creating technology support content for SupportYourTech.com.His work can be found on many websites and focuses on topics such as Microsoft Office, Apple devices, Android devices, Photoshop, and more.There are times when you may need to bypass a lost admin password through a reset of your Windows 10 PC to a clean slate. If youve been given an old PC with an existing user account, you may not have the details you need to wipe your PC and repurpose it. To factory reset Windows 10 without the admin password, youll need to follow these steps. If you dont have the admin password for a Windows PC, you can reset Windows 10 easily from the login screen. In the bottom-right corner of the login screen, youll see options to change your network settings, access Windows accessibility options, or power down your PC. To reset your Windows 10 PC, hold down the Shift key on your keyboard. With the key held down, press the Restart option under your power menu.This will reboot Windows 10, but rather than loading the operating system as normal, youll be presented with the boot options menu. Click the Troubleshoot option to proceed.In the Troubleshoot menu, click the Reset this PC option. You can choose to save your files or reset Windows 10 completely, removing all files and settings. To save your files, click the Keep my files option. Otherwise, click Remove everything instead. This will begin the process to reset your PC, and you may need to follow further on-screen instructions to proceed. Once the process is complete, youll be able to set up your Windows PC with a new user account, bypassing the old admin password entirely. The easiest method to factory reset your Windows 10 PC without the admin password is to use the method above. If your PC is having problems, however, you could decide to wipe the hard drive entirely, using Windows installation media to reinstall or reset Windows. You can download the Windows 10 installation disk image from the Microsoft website. You can burn this to a fresh DVD or flashed to a USB flash drive. If you have a second Windows 10 PC available, you can flash this ISO file to your USB drive using the Rufus flashing tool. Linux users can WoeUSB to do this, while macOS users could use the official Boot Camp Assistant app, which is installed on all Mac devices. If you have the Windows 10 ISO file and Rufus tool downloaded, open Rufus on your second Windows PC. Make sure your USB flash drive is selected in the drop-down menu, then click the Select button to select your ISO file.Select your Windows 10 installation ISO file from the file selection menu, then click Open.Rufus will automatically change its settings to match the requirements to flash a bootable USB Windows installation drive. Once youre happy with the settings, press the Start button to flash your drive. This will wipe it, so be sure to backup any important files saved on it before you begin.This will take a bit of time to complete. Once Rufus has finished flashing your USB flash drive, restart your PC to boot into the Windows installation screen. At the Windows installation screen, youll need to select the language to use during the installation process. Youll also need to select your time and currency locale, as well as the keyboard locale to use. Once youre ready to proceed, click the Next button.Click the Install now button to start the installation process.The Windows installation files will load at this point. You may need to provide a Windows 10 product key at this point to activate the installation, so type this key here. If you dont have a key, type the I dont have a product key option. Youll need to activate Windows after the installation is completed if you choose this option to reset your PC.If the option is available, select the version of Windows 10 you wish to install, then click the Next button.Youll need to accept the Windows 10 license agreement next. Click the I accept the license terms checkbox, then click Next to proceed.The installer will detect an existing Windows installation. To bypass the admin password, its better to choose the Custom: Install Windows only (advanced) option here. This will wipe all files from your PC before reinstalling Windows.Select the drive to install Windows at the next stage. If you have multiple partitions, you might need to delete and recreate these first. Select Next to continue. At this point, Windows will begin wiping your drive and copying files for the new installation. Windows will then reboot to begin the next stage of the installation process, allowing you to create a new user account once the process has completed to allow you to use the PC again. Some PC and laptop manufacturers include a special recovery partition drive that allows you to reset your Windows 10 PC by restoring your Windows 10 installation back to the factory default. This can usually be activated by restarting your PC and pressing a certain key on your keyboard during the boot-up process. The key you press will vary, depending on the device manufacturer. For instance, some HP computers require you to press and hold the F11 key on your keyboard as your PC boots. Source HP Each manufacturer has its own on-screen instructions for how to activate and trigger this process. Consult the user manual for your PC or laptop for any special instructions on how to use a recovery partition on your PC, as well as to determine the right key to press. If your PC doesnt have a recovery partition available, youll need to use one of the methods listed above to factory reset Windows 10 instead. Once you know how to reset Windows 10 without the admin password to hand, youre ready to start again. Your first task is to use a password manager to help you generate a secure password for your PC. You can set up Windows without a Microsoft account, but youll lose access to some additional Windows features. You could switch to a passwordless login on Windows 10 to be able to ditch passwords completely. Once your PC is reset and ready to use, youll need to think about the new software youll need to immediately install, from a new web browser to an antivirus to keep your PC safe from malware. Welcome to our guide on how to factory reset Windows 10 without a password. At some point, you may find yourself in a situation where you need to perform a factory reset on your Windows 10 computer. This process restores your system to its original factory settings, effectively wiping out all your personal data, installed programs, and settings.There are several scenarios where performing a factory reset can be helpful. For instance, if your computer is running slow, plagued by malware, or experiencing frequent crashes, a factory reset can provide a fresh start and potentially resolve these issues. Additionally, if youre planning to sell or donate your computer, performing a factory reset ensures that all your personal information is permanently removed.In Windows 10, there are multiple methods you can use to perform a factory reset, and in this guide, well walk you through each one. Whether you have a password or not, youll find a method that suits your needs.Keep in mind that a factory reset should be approached with caution, as it permanently deletes all your files and applications. Therefore, it is vital to backup any important data before proceeding with a factory reset. Once youve made sure your data is safely backed up, you can continue with the appropriate method for your situation.During the factory reset process, Windows 10 will be reinstalled, and your computer will be restored to its original state. Afterward, youll have a clean slate to set up your system again, reinstall your programs, and configure your settings.Please note that the exact steps and options may vary slightly depending on the specific version of Windows 10 you are using. However, the general steps and concepts outlined in this guide should apply to most Windows 10 installations.Now that you understand the purpose and importance of a factory reset, lets dive into the different methods you can use to reset Windows 10 without a password. Why would you want to factory reset Windows 10?There are several reasons why you might want to perform a factory reset on your Windows 10 computer. Lets explore some of the most common scenarios where this action can be beneficial.1. Slow performance: Over time, your computer may start to slow down due to various factors such as accumulated junk files, outdated drivers, or incompatible software. Performing a factory reset can help to eliminate these issues and restore your computers performance to its original state.2. System errors: If youre experiencing frequent system errors, crashes, or unexpected behavior, a factory reset can serve as a troubleshooting step. By reverting your system back to its factory settings, you can eliminate any software-related issues that may be causing the problems.3. Virus or malware infections: Despite taking precautions, your computer may become infected with viruses or malware that can compromise your security and privacy. Performing a factory reset removes all traces of these infections, ensuring a clean and secure system.4. Selling or donating your computer: Before selling or giving away your computer, it is crucial to remove all your personal data to protect your privacy. A factory reset completely erases your files, making them unrecoverable by ordinary means.5. Starting fresh: Sometimes, you may simply want to start fresh with a clean installation of Windows 10. This can be helpful if youve made significant changes to your system, installed a lot of software that you no longer need, or just want a clean slate to work with.6. Resolving software conflicts: If youre encountering conflicts between software programs or experiencing compatibility issues, a factory reset can help resolve these problems. By removing all programs and returning your system to its original state, you can start again with a clean and stable setup.Its important to note that performing a factory reset should be a last resort and is not always necessary to resolve issues on your computer. Before proceeding with a factory reset, its advisable to try other troubleshooting steps, such as updating drivers, running antivirus scans, or using system repair tools.Now that you understand the various reasons why you might want to perform a factory reset, lets move on to the different methods you can use to reset Windows 10 without a password. Method 1: Reset Windows 10 using the Settings appOne of the easiest ways to factory reset Windows 10 without a password is by using the built-in Settings app. This method is suitable for users who can still access their Windows desktop. Heres how you can do it:Click on the Start menu button and select the Settings cog icon.In the Settings window, click on the Update & Security option.In the left-hand menu, choose the Recovery tab.Under the Reset this PC section, click on the Get started button.A new window will appear with two options: Keep my files and Remove everything. Select the option that suits your needs.If prompted, you may be asked to enter your Windows 10 account password to proceed. However, if you dont have a password or have forgotten it, you can simply click on the Next button to continue.Windows 10 will then start the resetting process. This may take some time, so be patient.Once the process is complete, your computer will restart, and you will be presented with the initial setup screen, just like when you first purchased the device.Its important to note that the Keep my files option will preserve your personal files such as documents, pictures, and videos, while removing applications and settings. On the other hand, the Remove everything option will wipe out everything, including your personal files.Before proceeding with a factory reset using the Settings app, ensure that you have backed up all your important files and data, as they will be permanently deleted during the process.Once the resetting process is complete, you can proceed with setting up your Windows 10 system again, reinstalling any necessary applications, and configuring your preferences.Now that youre familiar with the first method of resetting Windows 10 without a password, lets move on to the next method. Method 2: Use the Windows Recovery Environment (WinRE) to reset Windows 10If youre unable to access your Windows desktop or the Settings app, you can still perform a factory reset using the Windows Recovery Environment (WinRE). This method is particularly useful when your computer is experiencing severe issues or wont boot properly. Heres how you can use WinRE to reset Windows 10 without a password:Start by restarting your computer. While its restarting, repeatedly press the F11 key (or the key specified by your computers manufacturer) to enter the Advanced Startup options.In the Advanced Startup menu, select Troubleshoot to access the troubleshooting options.Within the Troubleshoot menu, choose Reset this PC.You will be presented with two options: Keep my files and Remove everything. Select the option that best suits your needs.If prompted, enter your Windows 10 account password. However, if you dont have a password or have forgotten it, you can proceed without entering anything.Windows 10 will then begin the resetting process. Depending on the speed of your computer and the amount of data, this process may take some time.Once the process is complete, your computer will restart, and you will be guided through the initial setup screen as if you just purchased the device.Just like with the previous method, its crucial to back up all your important files and data before proceeding with a factory reset using WinRE, as your personal files will be permanently deleted during the process.The Windows Recovery Environment provides a powerful set of tools and options to help you troubleshoot and repair your Windows 10 installation. In addition to the factory reset feature, it also provides options for system restore, startup repair, and more.Now that youre familiar with using the Windows Recovery Environment to reset Windows 10 without a password, lets move on to the next method. Method 3: Reset Windows 10 using installation mediaIf youre unable to access the Settings app or the Windows Recovery Environment (WinRE), another method to perform a factory reset without a password is by using Windows installation media. This method is helpful when your computer is unable to boot or if you dont have access to the built-in recovery options. Heres how you can use installation media to reset Windows 10:Start by creating a Windows 10 installation media. You can do this by downloading the Windows 10 ISO file from Microsofts official website and using a tool like Rufus to create a bootable USB drive.Insert the USB drive with the Windows 10 installation media into your computer.Restart your computer and enter the BIOS or boot menu by pressing the appropriate key (usually F2, F8, or Del) during the startup process.In the BIOS or boot menu, change the boot order to prioritize the USB drive. Save the changes and exit the BIOS or boot menu.Follow the on-screen prompts to boot from the USB drive and start the Windows 10 installation process.When prompted, choose your language preferences and click Next.Click on the Repair your computer option located at the bottom-left corner of the installation window.In the Choose an option screen, select Troubleshoot and then choose Reset this PC.Choose the appropriate reset option for your needs: Keep my files or Remove everything.If required, enter your Windows 10 account password. However, if you dont have a password or have forgotten it, you can proceed without entering anything.Windows 10 will then initiate the resetting process, which may take some time depending on your computers performance and the amount of data being reset.Once the process is complete, your computer will restart, and you will be guided through the initial setup screen as if you just bought the device.Remember, before proceeding with a factory reset using installation media, ensure that you have backed up all your important files and data, as they will be permanently deleted during the process.Using Windows installation media provides you with the flexibility to reset Windows 10 without access to the operating system or the recovery options. It can be especially handy when other methods are not feasible or accessible.Now that youre familiar with the third method of resetting Windows 10 without a password, lets move on to the next method. Method 4: Reset Windows 10 without password using specialized softwareIf you dont have access to the Windows 10 Settings app, Windows Recovery Environment, or installation media, there are specialized software programs available that can help you reset Windows 10 without a password. These programs are designed specifically for this purpose and offer a user-friendly interface to guide you through the process. Heres how you can use specialized software to reset Windows 10:Start by researching and selecting a reputable password reset or recovery software program.Download and install the software on a separate computer that you can access.Launch the software and create a bootable USB drive or DVD using the instructions provided by the software.Insert the bootable USB drive or DVD into your locked Windows 10 computer.Restart your computer and enter the BIOS or boot menu by pressing the appropriate key (usually F2, F8, or Del) during the startup process.In the BIOS or boot menu, change the boot order to prioritize the USB drive or DVD. Save the changes and exit the BIOS or boot menu.Follow the on-screen prompts to boot from the USB drive or DVD and start the password reset software.Once the software has loaded, choose the option to reset your Windows 10 password.Specify the user account for which you want to reset the password.Follow the instructions provided by the software to complete the password reset process.Once the password has been reset, restart your computer and log in to your Windows 10 account using the new password.Its important to note that while specialized software can be effective in resetting Windows 10 passwords, its crucial to use reputable and trusted programs from reliable sources. Additionally, ensure that you follow the instructions provided by the software carefully to avoid any potential issues or data loss.Now that youre familiar with using specialized software to reset Windows 10 without a password, you have multiple options to choose from based on your specific needs and circumstances.In the next section, well offer some concluding remarks and recap the different methods discussed in this guide. ConclusionIn conclusion, performing a factory reset on Windows 10 can be a useful solution in various scenarios, such as when your computer is running slow, infected with malware, experiencing system errors, or if youre selling or donating your device. Resetting Windows 10 removes all your personal data, applications, and settings, restoring your computer to its original state.Throughout this guide, weve covered four different methods to reset Windows 10 without a password. These methods include using the Settings app, the Windows Recovery Environment (WinRE), installation media, and specialized software. Each method provides a unique approach that can be used depending on your specific situation and accessibility to different tools or options.Using the built-in Settings app is the most straightforward method if you can still access your Windows desktop. The Windows Recovery Environment (WinRE) is useful when your computer has severe issues or wont boot properly. Utilizing installation media allows you to perform a reset even without access to the operating system. Lastly, specialized software offers an alternative solution when other methods are not feasible.Before proceeding with a factory reset, its important to back up all your important files and data to prevent any loss. Once the reset process is complete, you can begin setting up your Windows 10 system again and reinstalling necessary applications.Remember, performing a factory reset is a serious action that permanently deletes your files and applications. It should be considered a last resort after exploring other troubleshooting options. If possible, seek assistance from technical experts or professionals if youre unsure about the process or facing significant challenges.We hope this guide has provided you with the necessary information to successfully reset Windows 10 without a password. By following the appropriate method for your situation, you can restore your computer to its original state and enjoy a fresh start. A factory reset can help you fix critical problems and improve your system performance. You can factory reset your PC using the Recovery option in the Settings app. However, to do this, you need to log in with an administrator account. But what if you have forgotten your administrator password or can't boot into your PC? For situations like this, Windows 11 offers a few alternative ways to factory reset your computer. You can factory reset Windows 11 without the admin password from the lock screen or by using a bootable Windows installation media. Let's explore the two ways you can bypass a Windows admin password and reset your PC. If your computer can boot normally but can't log in, you can reset your Windows 11 computer from the login screen. To do this, you'll need to boot into the Windows Recovery Environment (WinRE) to access Windows Advanced Startup Options. It consists of many troubleshooting tools, including the Reset this PC option that allows you to perform a reset without logging into your computer. Also, useful if you need to reinstall Windows 11 without deleting your personal files. This process will, however, remove your apps and settings. It is important to understand that you can reset the forgotten Windows administrator password using a nifty Linux hack and other workarounds. Only proceed with the steps below if your end goal is to factory reset your computer and not reset the forgotten admin password. To factory reset Windows 11 without an admin password using the Windows Recovery Environment: Turn on your PC and wait for the login screen to appear.In the bottom right corner, click on the Power options. It will show the Restart and Shutdown options. Don't click either just yet. Press and hold the Shift key on your keyboard and click the Restart button. If required, click on Restart Anyway to force restart your PC. Release the Shift key when you see the "please wait" screen. Your PC will now restart and enter the Windows Recovery Environment. In the Choose an option screen, click on the Troubleshoot option. In the Troubleshoot screen, click on Reset this PC. In the Reset this PC screen, you will be presented with two options. The Keep my files option will remove all the third-party apps and settings from your PC, but keep your personal files such as documents, media, etc. If you want to remove everything, then select Remove everything. Next, you will be presented with two options again to reinstall Windows. If you select Cloud Download, Windows will first download the required operating system files and then perform a reinstall. In comparison, Local Reinstall will use the existing system files from the device to reinstall Windows. To speed up the process, select Local reinstall. If that does not work, you can use the Cloud download option. In the Are you ready to reset this device screen, click on the Reset button to confirm the action and start the reset process. During the process, Windows will first reset your device to remove all the data, unless you have selected the Keep my files option, and then reinstall the operating system. It may take a while to complete the process, so leave your device idle and connected to the power outlet. If the reset process fails and requests additional system files, use the Cloud download option to perform a reset and try again. This often happens if your existing Windows installation is missing critical system files or corrupted. Using the Reset This PC option should help you bypass the Windows login password and reset the PC. However, if that does not work, you can clean install the Windows OS using a bootable USB drive. This is useful if you can't boot into Windows or the system image is damaged beyond repair. The Windows clean install process will wipe the hard drive erasing all the data. Make sure you have a backup of any important data before proceeding with the steps below. To clean install Windows 11, you'll need an installation media. So, create a Windows 11 bootable USB drive. Once you have the bootable drive ready, proceed with the below steps. Connect your Windows 11 installation media to the PC. Restart your PC and start pressing the F8, F9 or Esc key to open the Boot menu. In the Boot menu, select your USB flash drive as the boot drive and press Enter. If your computer does not support Boot Menu, youll have to change the boot order by accessing the BIOS or UEFI menu. Next, in the Window setup screen, select your language, time, currency format, and your preferred keyboard layout. Click Next to continue. Next, click the Install Now button. On the Activate Windows page, click the I dont have a product key link. Next, select the Windows 11 edition you want to install. If not, select the default option and click Next. Accept the terms and click Next. The setup wizard will detect your existing Windows installation and offer you to Upgrade. However, the upgrade option will keep your apps, settings, and admin password. So, select Custom: Install Windows only (advanced). Select your installation drive and click Next. Follow on-screen instructions to complete the installation. Windows will wipe your installation drive and install a fresh copy of the Windows OS. After the restart, Microsoft will prompt you to log in with your Microsoft account to complete the setup. If you have a Microsoft account, log in using the credentials and complete the setup. If you prefer to create and use a local user account instead, read our guide on how to install and set up Windows 11 without an internet connection and create one that way. Although you can factory reset the PC to bypass the admin password, setting up your system from scratch is cumbersome. To avoid this hassle, consider using a password manager. It not only stores difficult and long passwords and syncs them across devices but also protect them from hacker and other prying eyes with encryption. If you want to access your old laptop but youve forgotten its password, the ideal method is to factory reset it. Basically, this erases all your data, including the sign-in option, and restores the operating system to default. Generally, logging in to your laptop should be easy if you have set up a Microsoft Account. This is because you could easily reset your password even if forgotten. But you can possibly not do it if you got it from your friend or bought a pre-owned laptop. In such a case, the only option left is to restore it to factory settings. So, if youre also stuck on the sign-in screen and want to access the laptop, youre at the right place. Here, we have explained what a factory reset does and some easy techniques to do without a password. Factory reset is an option within Windows OS that sends the PC to its default system state. Usually, we perform the factory reset on Windows to solve any hard drive and OS-related issues. Since this option deletes every software thats creating issues on your system, we recommend factory resetting your laptop if youre trying to sell it or you recently bought a used one. This way, even the lagging issues get resolved, and you can use the old laptop as if its brand new. Factory resetting can be easily done within the Settings when youre already logged in to your laptop. Well, youll just need to go to System > Recovery > Reset This PC. Then, move ahead with the necessary steps. However, you need to use alternative methods if you do not remember your laptops password. In this section, we have explained the proven ways to factory reset your Windows 11 laptop. To enter the Windows Recovery Mode, we recommend checking the user manual as every manufacturer has different dedicated keys to open it. Generally, most PCs can navigate you to the recovery screen by pressing the F11 key when Windows is booting. Moreover, you can use bootable media and select Repair your computer to open the Windows Recovery Mode. Also, you can directly navigate to this screen from the login screen, and here are the involved steps you need to follow: Once youre on the log-in screen, press the power icon in the windows bottom-right corner.Now, while holding the Shift key, press the Restart option.Then, you may need to choose the Restart Now button if any other apps are running.Wait for several seconds until your system takes you to the Windows Recovery Mode.Once the Choose an option window loads, select Troubleshoot.Next, click on Reset this PC.Then, youll be shown two options Keep my files and Remove everything. If you want to keep your personal files, choose the first option. But if you want your laptop to restore everything to its default settings, select the latter.If you selected Remove everything, youd likely get two more options Cloud Download and Local Reinstall. Choose one as per your requirement.Again, youll need to select either Just remove my files or Fully clean the drive. Well, we suggest selecting the second option if you wish your entire system to be restored.Now, click on the Reset button to start the reset process. This may take more than an hour.Once the factory reset is complete, the setup window pops up. Now, you can move ahead and complete the system setup.Youll be asked to create a Microsoft account when this is completed. If you already have one, log in using your credentials. Otherwise, create an account and ensure you keep a password you remember. Interestingly, every manufacturer offers a recovery partition that can be accessed using a dedicated function key. Once you enter the recovery screen, youll be able to perform the following operations:Factory reset your laptopPerform backup and restore managementBack up user dataCreate a factory state diskCreate a disk copy In this section, we have included the steps for some of the most popular laptops. If we have missed out on yours, the process is quite similar to any of them. So, all you have to do is read the user manual or refer to the internet to check the dedicated key for your laptop. Samsung doesnt just manufacture mobile phones but is also equally popular for producing laptops. For demonstration purposes, we have used Samsung Notebook here. Nonetheless, the steps should be similar for every other Samsung laptop too: Power on your device and wait until the Samsung logo pops up.Now, long hold the F4 key, and youll notice a Please Wait signal on the screen.After several seconds, your laptop initiates Samsung Recovery.Wait until the Terms of Use page loads. Scroll down and click on the Agree button.Next, in the Samsung Recovery window, choose Computer factory reset.Then, check the Verify backup data option so that all your files and data will be backed up.Now, choose the Start factory reset option and wait until the reset is complete.Once the reset is complete, your PC restarts, where you can log in to your Microsoft account and set the desired password. Lenovo has adopted OneKey Recovery to factory reset your laptop without needing a password. However, this option is available only on the Ideapad series. For demonstration purposes, weve used the Lenovo G40 model. Nonetheless, the steps should be similar to other models as well: Find and press the Novo button thats generally located on the left side of your laptop. You may need a pointed object to press the button.Once the Novo Button Menu pops up, choose System Recovery. In some models, you can press the F10, F8, or F12 keys to navigate here.Wait for several seconds until the OneKey Recovery window opens up.Now, choose either Restore from initial backup or Restore from users backup and hit the Next button.Then, click the Start button to start a factory reset on your Lenovo laptop.Once the recovery is complete, set up Windows as per the screen instructions. Dell users can factory reset their laptops using the SupportAssist OS Recovery feature. However, this option is only available on some models. Go through the below guide to restore your

Options window will popup, click System Restore, it will check the data in your Restore Partition and factory reset laptop without password. Way 3. Reset Laptop without Password Using Recovery PartitionComputers nowadays usually come with a recovery partition preinstalled, or are shipped with a recovery disc when out of the box, which is used to do a factory reset on your laptop in case system failure happens. However, this may be a little tricky for an old OS version like Windows XP, Windows Vista. (See how to factory reset Windows 10 without password here)1. Power on or restart you laptop and hit the corresponding key repeatedly on startup screen. Below we have listed common keys for well-known manufacturers.Acer: Alt+F10Asus: F9Dell: F8HP: F11Lenovo: F11Samsung: F4Sony: F10Toshiba: 0 (not in numpad)2. After that, you will boot into the recovery partition or called Recovery Manager on some PC brands, in which screen you can find specific guidance on how to restore laptop to factory default. Here we take how to factory reset HP laptop without password as an example. Choose System Recovery under I need help immediately.3. Follow the instructions to restore your laptop to its original condition and when the reset is completed, restart the PC and decide the initial setup settings. Way 4. Remove Windows Password to Reset Laptop to Factory Settings without Password (100% Work)There is another possibility that you accidently forgot login password for Windows 7/8/10, and you are not allowed to reset default settings on laptop unless you have the right admin password. In this case, I will suggest you to remove login password with some password recovery software like Windows Password Key. Below I will show you how to unlock a laptop without password. Free Download Buy Now1. Install and launch Windows Password Key on another computer, and inset a CD/DVD/USB drive.2. Click burn to put ISO files into your drive and create a bootable reset disk.3. When finished, eject the device and plug it to your laptop needs factory resetting. Boot your laptop from the disk to enter password recovery interface.4. Choose the Windows Installation by the ID number demonstrated.5. Type the according number of Windows users to reset password.6. Type y to confirm password reset for user and eject the external drive, then reboot your laptop. You can now successfully enter the desktop without any password.7. After that, restore you laptop back to factory default settings with methods above.This is the end for how to reset laptop to factory settings without password. With 4 ways provided, you will hopefully find at least one workable. Free Download Buy Now Related ArticlesHow to Factory Reset A HP Laptop without Administrator PasswordHow to Restore Dell Laptop to Factory Settings without Admin PasswordHow to Reset Windows and BIOS Password on Laptop comments powered by A factory reset can be the solution to many problems in Windows 10/8/7. If your laptop is running slow or it has a virus, then factory resetting your Windows 10/8/7 computer might just be the right option for you. But, beware! A Windows factory reset will delete all the user data. And if you forgot Windows password, you may not be able to do it by the traditional way, so there is a question, how to factory reset Windows 10/8/7 laptop without password?Want to know how to factory reset a Windows 10/8/7 laptop without password. More on it below:Way 1: Factory Reset Windows 10/8/7 Laptop with Installation DiskWay 2: Factory Reset Windows 10/8/7 Laptop with Windows Password Recovery Tool Way 1: Factory Reset Windows 10/8/7 Laptop with Installation Disk If you cant access your Windows 10/8/7 because you do not remember the password, then follow these steps to factory reset Windows laptop without password:Insert the installation disk and turn on the computer.Press and hold F8 key.At Advanced Boot Options, choose Repair Your Computer.Press Enter.Select your preferred language and click Next.At the System Recovery Options choose System Restore.Follow the wizard instructions and you will successfully factory reset your Windows laptop without password!Way 2: Factory Reset Windows 10/8/7 Laptop with Windows Password Recovery Tool 2.1. Reset Windows Password with Windows Password Recovery Tool First Did the method above not work for you? Nothing to worry about. Another great way to factory reset Windows without knowing the password is to use Windows Password Recovery Tool, which helps you recover forgotten passwords in a few minutes, remove passwords without data loss or reset your passwords for Windows 10/8/7. You will need another computer where you can download the program so time to call in some favours! To use Windows Password Recovery Tool follow these steps: 10,000+ Downloads Key Features: It can recover forgotten password for all Windows in a few minutes. It can create a new administrator account easily without logon. It can create USB flash drive disk or CD/DVD Disc. Support Windows 10, 8.1, 8, 7, Vista, XP, 2000, NT. Support Windows Server 2016, 2012, 2008(R2), 2003(R2), 2000, NT. Free Download Buy Now Select whether you would prefer to create the password reset disk in a USB or a CD and click on Begin Burning.After the process has finished, insert the USB or disk into the computer you want to reset the password.Choose the profile of which you want to reset the password and click on Reset Password.Finally eject the password reset disk and click Reboot. The computer will restart and function normally. So now you can access your locked Windows 10/8/7 computer normally. Still want to factory reset it? Here is how to do it:Access the Settings menu.Click Update & Security, then Recovery.Now, choose Reset this PC.Next, click on Remove everything.Tap on Remove files and clean the drive to format the whole computer. This process will take long but it should leave it good as new technically speaking.Your Windows 10/8/7 laptop will reboot various times.Once its finished, you will have factory reset it successfully!SummaryIn this post, we showed you 2 different ways to factory reset Windows 10/8/7 laptop without password. Dont forget to like the post if it was useful and if you still have problems with your device dont hesitate to contact us. Free Download Buy Now If you want to access your old laptop but youve forgotten its password, the ideal method is to factory reset it. Basically, this erases all your data, including the sign-in option, and restores the operating system to default. Generally, logging in to your laptop should be easy if you have set up a Microsoft Account. This is because you could easily reset your password even if forgotten. But you can possibly not do it if you got it from your friend or bought a pre-owned laptop. In such a case, the only option left is to restore it to factory settings. So, if youre also stuck on the sign-in screen and want to access the laptop, youre at the right place. Here, we have explained what a factory reset does and some easy techniques to do without a password. Factory reset is an option within Windows OS that sends the PC to its default system state. Usually, we perform the factory reset on Windows to solve any hard drive and OS-related issues. Since this option deletes every software thats creating issues on your system, we recommend factory resetting your laptop if youre trying to sell it or you recently bought a used one. This way, even the lagging issues get resolved, and you can use the old laptop as if its brand new. Factory resetting can be easily done within the Settings when youre already logged in to your laptop. Well, youll just need to go to System > Recovery > Reset This PC. Then, move ahead with the necessary steps. However, you need to use alternative methods if you do not remember your laptops password. In this section, we have explained the proven ways to factory reset your Windows 11 laptop. To enter the Windows Recovery Mode, we recommend checking the user manual as every manufacturer has different dedicated keys to open it. Generally, most PCs can navigate you to the recovery screen by pressing the F11 key when Windows is booting. Moreover, you can use bootable media and select Repair your computer to open the Windows Recovery Mode. Also, you can directly navigate to this screen from the login screen, and here are the involved steps you need to follow: Once youre on the log-in screen, press the power icon in the windows bottom-right corner.Now, while holding the Shift key, press the Restart option.Then, you may need to choose the Restart Now button if any other apps are running.Wait for several seconds until your system takes you to the Windows Recovery Mode.Once the Choose an option window loads, select Troubleshoot.Next, click on Reset this PC.Then, youll be shown two options Keep my files and Remove everything. If you want to keep your personal files, choose the first option. But if you want your laptop to restore everything to its default settings, select the latter.If you selected Remove everything, youd likely get two more options Cloud Download and Local Reinstall. Choose one as per your requirement.Again, youll need to select either Just remove my files or Fully clean the drive. Well, we suggest selecting the second option if you wish your entire system to be restored.Now, click on the Reset button to start the reset process. This may take more than an hour.Once the factory reset is complete, the setup window pops up. Now, you can move ahead and complete the system setup.Youll be asked to create a Microsoft account when this is completed. If you already have one, log in using your credentials. Otherwise, create an account and ensure you keep a password you remember. Interestingly, every manufacturer offers a recovery partition that can be accessed using a dedicated function key. Once you enter the recovery screen, youll be able to perform the following operations:Factory reset your laptopPerform backup and restore managementBack up user dataCreate a factory state diskCreate a disk copy In this section, we have included the steps for some of the most popular laptops. If we have missed out on yours, the process is quite similar to any of them. So, all you have to do is read the user manual or refer to the internet to check the dedicated key for your laptop. Samsung doesnt just manufacture mobile phones but is also equally popular for producing laptops. For demonstration purposes, we have used Samsung Notebook here. Nonetheless, the steps should be similar for every other Samsung laptop too: Power on your device and wait until the Samsung logo pops up.Now, long hold the F4 key, and youll notice a Please Wait signal on the screen.After several seconds, your laptop initiates Samsung Recovery.Wait until the Terms of Use page loads. Scroll down and click on the Agree button.Next, in the Samsung Recovery window, choose Computer factory reset.Then, check the Verify backup data option so that all your files and data will be backed up.Now, choose the Start factory reset option and wait until the reset is complete.Once the reset is complete, your PC restarts, where you can log in to your Microsoft account and set the desired password. Lenovo has adopted OneKey Recovery to factory reset your laptop without needing a password. However, this option is available only on the Ideapad series. For demonstration purposes, weve used the Lenovo G40 model. Nonetheless, the steps should be similar to other models as well: Find and press the Novo button thats generally located on the left side of your laptop. You may need a pointed object to press the button.Once the Novo Button Menu pops up, choose System Recovery. In some models, you can press the F10, F8, or F12 keys to navigate here.Wait for several seconds until the OneKey Recovery window opens up.Now, choose either Restore from initial backup or Restore from users backup and hit the Next button.Then, click the Start button to start a factory reset on your Lenovo laptop.Once the recovery is complete, set up Windows as per the screen instructions. Dell users can factory reset their laptops using the SupportAssist OS Recovery feature. However, this option is only available on some models. Go through the below guide to restore your settings to default on a Dell laptop: Power on your PC and hit the F12 key multiple times to enter BIOS mode. In some models, you might need to use other keys. So, we suggest looking up the internet to check the key that works for you.Under Other Options, choose SupportAssist OS Recovery.Then, wait for about a minute until the feature loads and select Restore System.Next, click on the Restore Now button.Continue hitting Next until the Do you want to backup your file message appears. Choose Backup if you want to; else, you can choose Skip.Now, select a reason why youre performing the reset. Then, click on Next.Wait for the factory reset to complete and tap on the Finish button.Once the reset is complete, you can proceed with the instruction and install Windows. Generally, both resetting and reinstalling Windows are applicable if youre trying to delete everything from your PC. So, if you have an original disk or its feasible to create a bootable drive, you can easily reinstall your OS. To reinstall Windows using an installation media, youll need another Windows PC and an 8 GB or higher storage USB drive to make it bootable. Also, download Rufus from their official site as the below steps involve using this open-source application: Firstly, visit Microsofts official website on your other PC and download the Windows 11 ISO file.Now, launch Rufus and under Device, choose your flash drive.Next, under Boot selection, select the downloaded ISO file.Then, click on the START button to make your drive bootable.Once a warning message pops up, choose Ok.Unplug the USB cable and insert it into your laptop.Power on your laptop and wait until the Windows Setup window pops up.Next, choose the language, time, and keyboard. Then, select Next to continue.Now, click on the Install button.If you have the activation key, enter it. Else, you can choose I dont have a product key from the bottom of the dialogue box.Then, select the OS and proceed by clicking on Next.Check the Microsoft Software License Terms and again click on Next.Now, youll get two options Upgrade: Install Windows and keep files, settings, and applications and Custom: Install Windows only.If the supported version is already running, we recommend choosing the first option as this will reinstall Windows without losing data. Nonetheless, you can choose the latter one if you want the system to start from default.Then, choose a drive to create a partition. While doing so, ensure you delete all the other drives.Finally, wait for Windows to get installed. Once done, youll be navigated to a new window where you can set up a Microsoft account and start using the OS from scratch. Getting locked out of your HP laptop can feel like hitting a brick wall, especially when youre staring at the login screen and cant remember your password. Whether youre prepping the laptop for resale or Use Word, Excel, and PPT for FREE just trying to start fresh after being locked out, resetting without the password becomes the fastest way forward. In this guide Ill help you on how to factory reset HP laptop without password.How to Factory Reset HP Laptop Without PasswordUse HP Recovery Manager via Boot MenuIf your HP laptop still has its recovery partition intact, this method is one of the fastest ways to reset the device without needing a password. It works by triggering HPs built-in Recovery Manager through a simple key combination at startup. This bypasses the need to log in and takes you directly to the recovery interface. From there, you can choose to perform a full factory reset or troubleshoot specific issues. Its especially useful if youre locked out or preparing the laptop for resale. Just a few clicks, and your system will be restored to its original state. Heres how to factory reset HP laptop without password:Step 1: Turn off your HP laptop completely.Power Off LaptopStep 2: Hold down the Windows key and the B key together, then press the power button. Let go of the power button when you see the HP logo, but keep holding Windows + B until the system beeps or takes you to a recovery screen.Windows + B KeyStep 3: Select Troubleshoot and then Recovery Manager.Click TroubleshootStep 4: After Selecting the Recovery Options, go back to Troubleshoot and Click Reset This PC. Follow on screen instructions to reset your laptop.Reset PCThis method works because it bypasses the operating system entirely and connects to the recovery partition at the hardware level. If your HP laptop is from before 2018, you may need to use the F11 key instead of Windows + B when powering on. Use Word, Excel, and PPT for FREE Perform a Cloud Reset Using the HP Cloud Recovery ToolSometimes, the recovery partition is missing or corrupted, especially if the laptop has changed hands or the hard drive was replaced. In those cases, your best bet is to use HPs official Cloud Recovery Tool to build a fresh system from another PC.This method does take longer, but it guarantees a clean install with no leftover user data or settings. Here are some step by step instruction on how to hp laptop factory reset without password using cloud recovery tool:Step 1: On a different computer, go to the Microsoft store or HPs website and download the HP Cloud Recovery Tool.Step 2: Plug in a 32GB or larger USB drive and launch the tool(run as administrator).HP Cloud Recovery ToolStep 3: Let the tool create the recovery USB.Step 4: Insert the USB into your locked HP laptop and boot from it. To do this, turn on the laptop and press Esc, then F9 to select the USB drive as the boot source.Esc, F9 KeyStep 5: Follow the prompts to fully reset the device. Choose the option to remove all files for the cleanest install.This option is perfect if youre seeing recovery errors or if F11/Recovery Manager doesnt launch. Just be prepared, it can take 34 hours for the entire process, including setup.Remove Microsoft Account Lock After Reset Use Word, Excel, and PPT for FREE A full factory reset will erase your data, but it wont always unlink the device from the previous Microsoft account. If youre seeing a Verify your identity prompt or stuck at a login you cant bypass, youll need to take a few extra steps. This is especially common if youve purchased the laptop second-hand or if you're using Microsoft accounts to log in. Here are some step-by-step instructions on how to remove microsoft account lock after resetStep 1: During initial setup after the reset, enter a fake email like no@thankyou.com when prompted for a Microsoft login.Enter Fake EmailStep 2: Go to Accounts in Settings then click Access work or school.This is where any linked accounts are listed.Click Access work or schoolStep 3: Disconnect the old Microsoft account if it appears. Click on the profile and choose Disconnect.Disconnect Microsoft AccountStep 4: Go to System Settings, then to Activation, finally click on Troubleshoot.Troubleshoot ActivationThis step prevents your reset HP laptop from becoming locked again later and avoids frustrating This device is linked to another account messages. You can also explore registry edits if needed, but for most people, this method works just fine.WPS Office A Clean Productivity Suite Post-ResetAfter restoring your HP laptop, you probably want to reinstall the basics without overwhelming your system. WPS Office is one tool Ive used repeatedly on fresh installs because it doesnt slow things down. Its free, lightweight, and includes all the essentials without needing multiple apps. I installed WPS Office on an older HP laptop after doing a reset for a friend, and it ran smoothly right from the start. It didnt require any subscriptions or additional setup, just opened in the browser or Android app with everything I needed. Here are some tools that help right away:WPS Office ToolsWriter: Used this to jot down post-repair notes and organize files from the reset. It autosaves to the cloud and opens DOCX files instantly.Spreadsheet: Handy for tracking repair timelines or documenting steps for others. The built-in formulas helped simplify tasks.Presentation: Pulled together a slide deck for a class using screenshots from the reset process.PDF: Opened and merged warranty files, how-to screenshots, and other documents into a single PDF. Annotating was easy.AI Resume Assistant: Helped tweak a resume for a client using just basic prompts.Grammar Check: Cleaned up some rough notes Id drafted during the repair.AI Slides Creator: Took my list of bullet points and gave me a usable presentation draft in seconds.PDF Summary Tool: Pulled key insights from long support documents so I could focus on just the relevant parts.WPS Office doesnt pretend to replace every app, but it fits nicely in a system that just went through a reset. Especially if your device has minimal RAM or you're trying to avoid heavy software installs, its a reliable productivity option that doesnt require much from your system.FAQsQ1: Will a factory reset remove viruses from my HP laptop?Yes, especially if you choose Remove everything and then select Clean the drive. This ensures that all user data is wiped and reformatted.Q2: What if the F11 key or HP Recovery Manager doesnt launch?Use the Cloud Recovery Tool method covered in Part 2. It works even if the recovery partition is missing or damaged.Q3: Does resetting the laptop bypass BitLocker encryption?No. If BitLocker is enabled, youll still need the 48-digit recovery key. Without it, the drive remains inaccessible.Q4: Can I get files back after a factory reset if I didnt back them up?Not easily. Youd need to remove the drive and use a recovery service, which isnt guaranteed. Always backup before resetting if you can.In this guide, I showed you how to factory reset HP laptop without password. You learned how to use built-in recovery tools, create a USB-based cloud reset, and unlink Microsoft accounts for a clean start, and once everythings up and running again, installingWPS Officegives you an easy way to get back to work without installing multiple programs. Its fast, efficient, and doesnt get in the way, just like your reset HP laptop should be. 100% secure Factory resetting a Windows 10 laptop without a password might seem daunting, but its a straightforward process. Youll be using the built-in troubleshooting tools to restore your laptop to its original state. Heres a quick overview: Restart your laptop, access the Advanced Startup options, navigate to the Reset your PC feature, and follow the on-screen instructions. This will wipe all data and reinstall Windows 10, bringing your laptop back to factory settings. This tutorial will guide you through the necessary steps to reset your Windows 10 laptop to its factory settings without needing a password. This process will delete all your files, so make sure to back up any important data before starting. Restart your laptop to begin the process. Restarting your laptop ensures that all running processes are halted, and you can smoothly access the needed system settings. Press and hold the Shift key while you click on the Restart option. Holding the Shift key while restarting takes you directly into the Advanced Startup options menu, bypassing the usual boot sequence. Once in Advanced Startup, select Troubleshoot from the menu. The Troubleshoot option provides various system recovery tools, making it easier to reset your PC without needing a password. Choose Reset this PC from the Troubleshoot menu. This option allows you to reset your laptop to its original factory settings, erasing all personal data and installed programs. Opt for the Remove everything option when prompted. By selecting Remove everything, you ensure that all files, settings, and apps are wiped from the system, providing a clean slate. Follow the on-screen instructions to confirm and start the reset process. The system will guide you through a few confirmation screens to make sure you want to proceed. Once confirmed, the reset will begin. After completing these steps, your laptop will restart several times and eventually boot up to the initial Windows 10 setup screen. Youll need to go through the setup process as if youre using the laptop for the first time. Make sure to back up any important files before starting the reset process, as all data will be lost. Keep your laptop plugged into a power source to avoid interruptions during the reset. Ensure you have a stable internet connection if you need to download updates after the reset. If your laptop came with a recovery USB or disc, keep it handy in case you encounter issues. Read through all on-screen instructions carefully to avoid accidental data loss. No, a factory reset will erase all data and return your laptop to its original settings. The process can take anywhere from 30 minutes to several hours, depending on your laptops speed and data size. No, Windows 10 should automatically activate if it was previously activated on your device. Yes, a factory reset will remove all files, including any malware. Its not recommended to stop the reset once it has started, as it can cause system errors. Restart your laptop. Press and hold the Shift key while clicking Restart. Select Troubleshoot. Choose Reset this PC. Select Remove Everything. Confirm the reset process. Factory resetting your Windows 10 laptop without a password is a handy skill to have, especially if youre dealing with performance issues or preparing your device for a new user. This process, while involving a few steps, is straightforward and designed to make your laptop feel brand new. Remember to back up your data beforehand to avoid any data loss. For further reading, check out more detailed guides on Microsofts official support pages or tech forums. Need more help? Feel free to reach out to professional tech support services. Factory resetting your laptop can solve a plethora of issues, so dont hesitate to give it a try if youre facing persistent problems. Happy resetting!Matthew Burleigh has been writing tech tutorials since 2008. His writing has appeared on dozens of different websites and been read over 50 million times.After receiving his Bachelors and Masters degrees in Computer Science he spent several years working in IT management for small businesses. However, he now works full time writing content online and creating websites.His main writing topics include iPhones, Microsoft Office, Google Apps, Android, and Photoshop, but he has also written about many other tech topics as well.Read his full bio here.

How do you factory reset a laptop if you don't know the password. How do i factory reset my computer without a password. How do i reset my acer laptop to factory settings without a password. How do i factory reset my hp laptop without a password. How to factory reset laptop without password. Can you factory reset a laptop without password. How do i factory reset my dell laptop without a password. Factory reset pc without logging in. Is there a way to factory reset a laptop without password. Reset laptop password without losing data.

- ba 2nd year environment book pdf in english
- conveyor design standards
- https://dcmheavyequipment.com/admin/images/file/3739102e-ac8d-422b-87dc-715bb8a8b82f.pdf
- xutobizawa
- https://dailyiat.com/html_upload/file/16066066370.pdf
- https://armature.ir/cache/fck_files/file/gumijakepuwoxa_maxadefi_jemipowose_relekosapifuvo.pdf